

Nepali Typing (Preeti Font)

क	ख	ग	घ	ङ
s	v	u	3	alt + 0170
च	छ	ज	झ	ञ
r	5	h	em	`
ट	ठ	ड	ढ	ण
6	7	8	9	Of
त	थ	द	ध	न
t	y	b	w	g
प	फ	ब	भ	म
k	km	a	e	d
य	र	ल	व	श
o	/	n	j	z
ष	स	ह	क्ष	त्र
if	;	x	lf	q
ज्ञ				
1				

का	=	f
कि	=	l with out shift
की	=	L with shift
कु	=	' without shift
कू	=	" With shift
के	=] without shift
कै	=] with shift
को	=	f] without shift
कौ	=	f] with shift
कं	=	+ with shift
कः	=	M withshift

”	=	Alt + 0198
“	=	Alt + 0230
'	=	Alt + 0218
‘	=	Alt + 0133
/	=	Alt + 0247
=	=	Alt + 0214
%	=	Alt + 0220
!	=	Alt + 0219
-	=	Alt + 0150
+	=	Alt + 0177
^	=	Alt + 0171
~	=	Alt + 0165
ह	=	Alt + 0197
ॠ	=	Alt + 0205
ॡ	=	Alt + 0221
ॢ	=	Alt + 0182
ॣ	=	Alt + 0167
।	=	Alt + 0203
॥	=	Alt + 0155
०	=	Shift + >
१	=	Alt+0163
२	=	Alt +0137
३	=	Alt +0136
४	=	Shift+ F

अ आ इ ई उ ऊ ऋ
c cf O O[p pm C

ए ऐ ओ औ अं अः
P P] cf] cf} c+ cM

Some Solution in Nepali typing

1. How To make ()

- ☺ Click On Office button .
- ☺ Click on 'Word Option'
- ☺ Click On Proofing Option.
- ☺ Click on 'Auto correct Options.'
- ☺ Choose 'Auto format as you type.'
- ☺ Unmark 'Straight quotes' with 'smart quotes'
- ☺ Click On ok / ok

Note : You can also solve this Problem by pressing Ctrl + Z.

2. यदि नेपाली लेख्ने समयमा सुरुको अक्षर आधा आयो भने के गर्ने ?

- ☺ Click on Office button.
- ☺ Click on word option.
- ☺ Click on Proofing Option.
- ☺ Click on Auto Correct Option.
- ☺ Unmark "Capitalize first letter of Sentence"

Note : You can also solve this Problem by pressing Ctrl + Z.

3. How to insert Nepali Page Number?

- ☺ At first go to insert Menu and click on Page Number Option.
- ☺ You can see page number on your page.
- ☺ Select the page number and go to font box. And type (fontasy Himali)
- ☺ Press Enter.